


# PROJECT: WFAC2X2

## FIRMWARE RELEASE NOTE



Document Information	
Project Number/Name:	WFAC2x2
Customer:	SiFlower
Customer Representative:	Franklin Wang
Catena Representative:	Jingbin Wang
Project Leader:	Jingbin Wang
Author:	Ajay Peter
Document Number:	
Revision Number:	0.1
Status:	Accepted

# Revision Control

Revision	Author	Purpose and Brief Summary of Changes	Date
0.1	Ajay Peter	Describe firmware release R1.3.002	Feb 26, 2021

## Disclaimers

The information contained in this document must be treated according the classification as indicated in the document footer. See for explanation of the possible classifications the list below.

## Document Classification

**Confidential:** Documents that may only be shared only to those persons authorized; MT, project team and/or with the customer under NDA. Do not leave these documents lying about open and unattended on tables, etc.

**Company Restricted:** For internal use only – can only be distributed and shared within Catena.

**Catena Proprietary:** Protected by trademark or patent or copyright; These documents can be shared but nobody is allowed to copy or use any information out of it without having the permission of the MT of Catena.

In case a document has no specified classification the information contained is at least Catena Proprietary.

## Trademarks

Catena recognizes all brand and product names as trademarks or registered trademarks of their respective holders.

# Table of Contents

<b>1</b>	<b>INTRODUCTION .....</b>	<b>4</b>
1.1	DOCUMENT PURPOSE AND SCOPE .....	4
1.2	REFERENCES .....	4
1.3	ABBREVIATIONS AND DEFINITIONS.....	4
<b>2</b>	<b>RELEASE PACKAGE.....</b>	<b>5</b>
2.1	VERSION IDENTIFICATION .....	5
2.2	PACKAGE CONTENT .....	5
<b>3</b>	<b>RELEASE CONTENT .....</b>	<b>6</b>
3.1	GOAL.....	6
3.2	SUPPORTED FUNCTIONALITY .....	6
<b>4</b>	<b>KNOWN PROBLEMS &amp; LIMITATIONS.....</b>	<b>7</b>

# 1 INTRODUCTION

## 1.1 Document Purpose and Scope

This document describes the content of the firmware releases for the WFAC2x2 project, variant Begonia.

## 1.2 References

Table 1-1 References

Doc #	Reference	Name	Date
19CAIN01_C06S017	[UM]	User Manual v1.1	Dec 10, 2019
17CAIN09_C06S009	[AMG]	API Migration Guide v1.0	Sept 25, 2019

## 1.3 Abbreviations and Definitions

Table 1-2 Abbreviations

Abbreviation	Meaning

Table 1-3 Definitions

Definitions	Meaning

## 2 RELEASE PACKAGE

### 2.1 Version Identification

Identifier	Value
target	BE
firmware version	R1.3.002

For this release, the GetVersion command will reply with the following information:

Identifier	Value
hw_major	50
hw_minor	C0
target_ver	2
fw_major	1
fw_minor	3
Build_nr	2
Test_nr	0

### 2.2 Package Content

The release package contains the following files:

File	Description
WFAC22_50C0_prog.mem	Program memory file, to be loaded by the host
WFAC22_50C0_init.mem	Initialization file, to be loaded by the host

Please follow the load and boot instructions as explained in the [UM].

## 3 RELEASE CONTENT

### 3.1 Goal

This firmware may be used for the Begonia target.

This firmware is intended to prevent errors seen when *rf\_set\_channel* is repeated several times.

Other changes include:

- Fixed: LB High Latency Command error sets wrong interrupt source.
- Added feature to synchronise the ADC clock

### 3.2 Supported Functionality

The table below shows which commands are part of this release, and if there are limitations for the command in this release.

**Table 3-1 command overview**

Command	Status
GEN_GetVersion	Functional
GEN_SetProperty	Functional
GEN_GetProperty	Functional
APP_GetStatus	Functional
APP_Activate	Functional
APP_Deactivate	Functional
APP_GetTemperature	Functional
APP_Calibrate	Functional
APP_CalResistor	Functional
APP_SetResistor	Functional
APP_ConfigTrx	Functional
APP_ConfigFemCtrl	Functional
CLK_SetXo	Functional
TRX_Receive	Functional
TRX_Transmit	Functional
TRX_Stop	Functional
TRX_Park	Functional
TRX_Prepare	Functional
TRX_GetStatus	Functional
TRX_SetDsmLoopDeltaLo	Functional
TRX_SetTestDc	Functional

## 4 KNOWN PROBLEMS & LIMITATIONS

None.